

Calculating 8-Hour Ozone Design Values

AQS Conference, June 19, 2007
Pittsburgh, PA

Lance O. McCluney
United States Environmental Protection Agency
Office of Air Quality Planning and Standards
Air Quality Assessment Division
Air Quality Analysis Group
Research Triangle Park, NC

Agenda

- What is the 8-hour ozone National Ambient Air Quality Standard?
- How do we calculate ozone 8-hour design values?
- Questions and Answers

What is the 8-hour ozone National Ambient Air Quality Standard?

Background


- The Clean Air Act requires EPA to set National Ambient Air Quality Standards (NAAQS) for ground-level ozone and five other criteria pollutants. The Clean Air Act established two types of national air quality standards for ground-level ozone.
 - Primary standards set limits to protect public health, including the health of "sensitive" populations such as asthmatics, children, and the elderly.
 - Secondary standards set limits to protect public welfare, including protection against visibility impairment, damage to animals, crops, vegetation, and buildings.
- The National Ambient Air Quality Standard for ozone can be found 40 CFR Part 50
- Appendix I to 40 CFR Part 50 interprets the 8-hour Primary and Secondary National Ambient Air Quality Standards for Ozone specified in Section 50.10
- In April 2004, EPA, using 2001-2003 data, designated 126 areas as nonattainment for the 8-hour ozone standard.

How do we calculate ozone 8-hour design values?

Running 8-hour averages

- Use hourly ozone concentrations
- A valid 8-hour average is one with at least 75% of the hourly data available
 - If there are only 6 or 7 hourly averages, divide by 6 or 7
 - Don't ignore 8-hour periods with less than 6 hours
 - Substitute $\frac{1}{2}$ the minimum detectable limit (MDL) for missing hourly concentrations. After the substitution, if the 8-hour average is greater than the level of the standard keep the 8-hour average.
- The 8-hour average is reported to three decimal places, and insignificant digits to the right of the third decimal place are truncated.

Example of Calculating 8-Hour Averages



How do we calculate ozone 8-hour design values?

Daily Maximum 8-hour average concentrations

- 24 possible running 8-hour average ozone concentrations for each calendar day during the ozone season.
- The daily maximum is the highest of the 24 possible 8-hour averages.
- A valid day is defined as one with at least 75% of the possible 8-hour averages in the day (18 of the 24 averages)
- If a day is less than 75% complete, the day is counted valid if the daily maximum is greater than the level of the standard

How do we calculate ozone 8-hour design values?

Summary Statistic

- The standard-related summary statistic is the annual fourth-highest daily maximum 8-hour ozone concentration averaged over three years, also known as the design value.
- The three year average is expressed to three decimal places, and any remaining digits to the right are truncated.

How do we calculate ozone 8-hour design values?

Comparisons with the Primary and Secondary Standards

- The standards are met when the 3-year average is less than or equal to 0.08 ppm
 - Rounding Convention: The third decimal place of the computed 3-year average is rounded. Thus, a computed 3-year average of 0.085 ppm is smallest value greater than 0.08 ppm.
- Completeness Criteria
 - A monitor has to have three consecutive complete calendar years of monitoring data.
 - A monitor has to have 75% of the valid days in ozone season for each year and a average of 90% for the three years
 - Years with concentrations greater than the level of the standard shall not be ignored due to having less than complete data.

The End

- Questions
- Contact Information
 - Lance McCluney, 919-541-4820,
mccluney.lance@epa.gov